

# Natural System Error Messages

## NAT8201-NAT8250

### NAT8201: Invalid program switch to a conversational transaction.

Text	Invalid program switch to a conversational transaction.
Expl.	A direct switch to a conversational transaction from a non-conversational one is not allowed. Module(s): NIIDIRTX
Actn.	Check the transaction codes used. OR Use the appropriate switching module.

### NAT8210: No free work PCBs.

Text	No free work PCBs.
Expl.	You cannot create a report because there is no free work PCB. Note: A work PCB is allocated to each open report. Module(s): NATAM06
Actn.	Increase the number of work PCBs in the transaction code table (WRKPCBS parameter in the NIMTRNTG macro). OR Decrease the number of parallel reports.

### NAT8211: Destination :1: for printing the report is not defined.

Text	Destination :1: for printing the report is not defined.
Expl.	The destination specified in the NTPRINT macro or in the OUTPUT parameter of the DEFINE PRINTER statement is not a valid IMS/TM destination. Module(s): NATAM06
Actn.	Check your destination. OR Contact your system programmer.

### NAT8212: Line length larger than block size.

Text	Line length larger than block size.
Expl.	The current print line is larger than the block size for the printer destination used. Module(s): NATAM06
Actn.	Increase the block size (BLKSIZE parameter in the NTPRINT macro). OR Decrease the line size for the report.

### NAT8250: Not enough space for the command in the command buffer.

Text	Not enough space for the command in the command buffer.
Expl.	<p>The length of the command passed is larger than the size of the command buffer.</p> <p>Note:</p> <p>The command buffer is used as I/O area when CMCMMND sends the command to IMS/TM.</p> <p>Module(s): CMCMMND</p>
Actn.	<p>Check the length of the command passed to CMCMMND</p> <p>OR Increase the size of the command buffer in the environment table (CMBSIZE parameter in the NIMPARM macro).</p>